

LibTopoART

v0.50

Generated by Doxygen 1.8.5

Fri Nov 1 2013 14:37:35

Contents

1 Namespace Index	1
1.1 Namespace List	1
2 Hierarchical Index	3
2.1 Class Hierarchy	3
3 Class Index	5
3.1 Class List	5
4 Namespace Documentation	7
4.1 Package LibTopoART	7
4.2 Package LibTopoART_samples	8
5 Class Documentation	9
5.1 LibTopoART.Episodic_TopoART Class Reference	9
5.1.1 Detailed Description	10
5.1.2 Constructor & Destructor Documentation	10
5.1.2.1 Episodic_TopoART	10
5.1.2.2 Episodic_TopoART	10
5.1.3 Member Function Documentation	10
5.1.3.1 Learn	10
5.1.4 Member Data Documentation	10
5.1.4.1 file_format_version	10
5.2 LibTopoART_samples.Episodic_TopoART_sample1 Class Reference	11
5.2.1 Detailed Description	11
5.3 LibTopoART.F2_output Class Reference	11
5.3.1 Detailed Description	11
5.3.2 Constructor & Destructor Documentation	12
5.3.2.1 F2_output	12
5.3.3 Member Data Documentation	12
5.3.3.1 bm_cluster_ID	12
5.3.3.2 bm_node_activation	12
5.3.3.3 bm_node_ID	12

5.3.3.4	bm_permanent_cluster_ID	12
5.3.3.5	bm_permanent_node_activation	12
5.3.3.6	bm_permanent_node_ID	12
5.4	LibTopoART.Fast_TopoART Class Reference	12
5.4.1	Detailed Description	13
5.4.2	Constructor & Destructor Documentation	13
5.4.2.1	Fast_TopoART	13
5.4.2.2	Fast_TopoART	13
5.4.3	Member Function Documentation	13
5.4.3.1	Learn	13
5.5	LibTopoART.Fast_TopoART_Base Class Reference	14
5.5.1	Detailed Description	15
5.5.2	Member Function Documentation	15
5.5.2.1	ComputeClusterIDs	15
5.5.2.2	GetBMOOutput	15
5.5.2.3	Learn	15
5.5.2.4	Save	15
5.5.2.5	SaveText	16
5.5.3	Member Data Documentation	16
5.5.3.1	file_format_version	16
5.5.3.2	float_base_type	16
5.5.3.3	integer_base_type	16
5.6	LibTopoART.ITopoART Interface Reference	16
5.6.1	Detailed Description	17
5.6.2	Member Function Documentation	17
5.6.2.1	ComputeClusterIDs	17
5.6.2.2	GetBMOOutput	17
5.6.2.3	Learn	18
5.6.2.4	Save	19
5.6.2.5	SaveText	19
5.7	LibTopoART.ITopoART_R Interface Reference	19
5.7.1	Detailed Description	19
5.7.2	Member Function Documentation	19
5.7.2.1	Learn	20
5.7.2.2	Predict	21
5.8	LibTopoART.LibTopoART_info Struct Reference	21
5.8.1	Detailed Description	21
5.8.2	Member Data Documentation	21
5.8.2.1	networks	21
5.8.2.2	version	22

5.9	LibTopoART.TopoART Class Reference	22
5.9.1	Detailed Description	23
5.9.2	Constructor & Destructor Documentation	23
5.9.2.1	TopoART	23
5.9.2.2	TopoART	24
5.9.3	Member Function Documentation	24
5.9.3.1	ComputeClusterIDs	24
5.9.3.2	GetBMOOutput	24
5.9.3.3	Learn	24
5.9.3.4	Save	24
5.9.3.5	SaveText	24
5.9.4	Member Data Documentation	25
5.9.4.1	file_format_version	25
5.9.4.2	float_base_type	25
5.9.4.3	integer_base_type	25
5.9.4.4	x_F0	25
5.9.4.5	x_F0_dim	25
5.10	LibTopoART.TopoART_R Class Reference	25
5.10.1	Detailed Description	26
5.10.2	Constructor & Destructor Documentation	26
5.10.2.1	TopoART_R	26
5.10.2.2	TopoART_R	26
5.10.3	Member Function Documentation	26
5.10.3.1	Learn	26
5.10.3.2	Predict	27
5.10.4	Member Data Documentation	27
5.10.4.1	file_format_version	27
5.11	LibTopoART.TopoART_R_Prediction Class Reference	27
5.11.1	Detailed Description	28
5.11.2	Constructor & Destructor Documentation	28
5.11.2.1	TopoART_R_Prediction	28
5.11.3	Member Function Documentation	28
5.11.3.1	PrintPredictions	28
5.11.4	Member Data Documentation	28
5.11.4.1	d_vec_prediction	28
5.11.4.2	i_vec_prediction	28
5.11.4.3	NO_PREDICTION	28
5.12	LibTopoART_samples.TopoART_R_sample1 Class Reference	28
5.12.1	Detailed Description	28
5.13	LibTopoART_samples.TopoART_sample1 Class Reference	28

5.13.1 Detailed Description	29
5.14 LibTopoART_samples.TopoART_sample2 Class Reference	29
5.14.1 Detailed Description	29

Index	30
--------------	-----------

Chapter 1

Namespace Index

1.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

LibTopoART	7
LibTopoART_samples	8

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

LibTopoART_samples.Episodic_TopoART_sample1	11
LibTopoART.F2_output	11
LibTopoART.ITopoART	16
LibTopoART.Fast_TopoART_Base	14
LibTopoART.Episodic_TopoART	9
LibTopoART.Fast_TopoART	12
LibTopoART.TopoART	22
LibTopoART.TopoART_R	25
LibTopoART.ITopoART_R	19
LibTopoART.TopoART_R	25
LibTopoART.LibTopoART_info	21
LibTopoART.TopoART_R_Prediction	27
LibTopoART_samples.TopoART_R_sample1	28
LibTopoART_samples.TopoART_sample1	28
LibTopoART_samples.TopoART_sample2	29

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

LibTopoART.Episodic_TopoART	
Class Episodic_TopoART provides an implementation of the Episodic TopoART neural network as proposed in "Marko Tscherpanow, Sina Kühnel, and Sören Riechers, 'Episodic Clustering of Data Streams Using a Topology-Learning Neural Network', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 24-29, 2012."	9
LibTopoART_samples.Episodic_TopoART_sample1	
Sample using artificial two-dimensional data	11
LibTopoART.F2_output	
Class F2_output provides the output of a single TopoART module. It is a compressed version of the output vectors y and c.	11
LibTopoART.Fast_TopoART	
Class Fast_TopoART provides an implementation of the TopoART neural network as proposed in "Tscherepanow, Marko (2010). TopoART : A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."	12
LibTopoART.Fast_TopoART_Base	
Base class providing functionality common to several TopoART networks.	14
LibTopoART.ITopoART	
Interface summarising the basic TopoART functionality.	16
LibTopoART.ITopoART_R	
Interface summarising the basic TopoART-R functionality.	19
LibTopoART.LibTopoART_info	
Struct LibTopoART_info provides some metainformation regarding the respective implementation of LibTopoART .	21
LibTopoART.TopoART	
Class TopoART provides an implementation of the TopoART neural network as proposed in "Tscherepanow, Marko (2010). TopoART : A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."	22
LibTopoART.TopoART_R	
Class TopoART_R provides an implementation of the TopoART-R neural network as proposed in "Tscherepanow, Marko (2011). An Extended TopoART Network for the Stable On-Line Learning of Regression Functions. In Proceedings of the International Conference on Neural Information Processing, LNCS 7063 (pp. 562–571). Berlin, Germany: Springer	25
LibTopoART.TopoART_R_Prediction	
Class F2_output contains a prediction made by a TopoART-R network.	27

LibTopoART_samples.TopoART_R_sample1	
Function approximation using TopoART-R	28
LibTopoART_samples.TopoART_sample1	
Simple TopoART sample	28
LibTopoART_samples.TopoART_sample2	
Sample using artificial two-dimensional data	29

Chapter 4

Namespace Documentation

4.1 Package LibTopoART

Classes

- class [Episodic_TopoART](#)

Class [Episodic_TopoART](#) provides an implementation of the Episodic [TopoART](#) neural network as proposed in "Marko Tscherepanow, Sina Kühnel, and Sören Riechers, 'Episodic Clustering of Data Streams Using a Topology-Learning Neural Network', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 24-29, 2012."

- class [Fast_TopoART](#)

Class [Fast_TopoART](#) provides an implementation of the [TopoART](#) neural network as proposed in "Tscherepanow, Marko (2010). [TopoART](#): A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

- class [Fast_TopoART_Base](#)

Base class providing functionality common to several [TopoART](#) networks.

- struct [LibTopoART_info](#)

Struct [LibTopoART_info](#) provides some metainformation regarding the respective implementation of [LibTopoART](#).

- class [F2_output](#)

Class [F2_output](#) provides the output of a single [TopoART](#) module. It is a compressed version of the output vectors y and c .

- class [TopoART_R_Prediction](#)

Class [F2_output](#) contains a prediction made by a [TopoART-R](#) network.

- interface [ITopoART](#)

Interface summarising the basic [TopoART](#) functionality.

- class [TopoART](#)

Class [TopoART](#) provides an implementation of the [TopoART](#) neural network as proposed in "Tscherepanow, Marko (2010). [TopoART](#): A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

- interface [ITopoART_R](#)

Interface summarising the basic [TopoART-R](#) functionality.

- class [TopoART_R](#)

Class [TopoART_R](#) provides an implementation of the [TopoART-R](#) neural network as proposed in "Tscherepanow, Marko (2011). An Extended [TopoART](#) Network for the Stable On-Line Learning of Regression Functions. In Proceedings of the International Conference on Neural Information Processing, LNCS 7063 (pp. 562–571). Berlin, Germany: Springer."

4.2 Package LibTopoART_samples

Classes

- class [Episodic_TopoART_sample1](#)
Sample using artificial two-dimensional data.
- class [TopoART_R_sample1](#)
Function approximation using TopoART-R.
- class [TopoART_sample1](#)
Simple TopoART sample.
- class [TopoART_sample2](#)
Sample using artificial two-dimensional data.


Chapter 5

Class Documentation

5.1 LibTopoART.Episodic_TopoART Class Reference

Class [Episodic_TopoART](#) provides an implementation of the Episodic [TopoART](#) neural network as proposed in "Marko Tscherepanow, Sina Kühnel, and Sören Riechers, 'Episodic Clustering of Data Streams Using a Topology--Learning Neural Network', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 24-29, 2012."

Inheritance diagram for LibTopoART.Episodic_TopoART:



Public Member Functions

- [Episodic_TopoART](#) (long input_dimension, long module_number, decimal rho_a_value, long t_max_value)
This constructor initialises an Episodic [TopoART](#) network.
- [Episodic_TopoART](#) (string path)
This constructor loads a saved Episodic [TopoART](#) network.
- override void [Learn](#) (decimal[] input)
This method performs a single training step.

Static Public Attributes

- new static readonly decimal [file_format_version](#) =0.01m
Instance variable [file_format_version](#) represents the version of the file format used by class [Episodic_TopoART](#).

Properties

- long [T_max](#) [get]
Property [T_max](#) represents the considered time frame.

5.1.1 Detailed Description

Class [Episodic_TopoART](#) provides an implementation of the Episodic [TopoART](#) neural network as proposed in "Marko Tscherepanow, Sina Kühnel, and Sören Riechers, 'Episodic Clustering of Data Streams Using a Topology-Learning Neural Network', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 24-29, 2012."

5.1.2 Constructor & Destructor Documentation

5.1.2.1 [LibTopoART.Episodic_TopoART.Episodic_TopoART \(long input_dimension, long module_number, decimal rho_a_value, long t_max_value \)](#)

This constructor initialises an Episodic [TopoART](#) network.

Parameters

<i>input_dimension</i>	The dimension of input vectors to be learnt.
<i>module_number</i>	The number of Episodic TopoART modules.
<i>rho_a_value</i>	The vigilance parameter of the first Episodic TopoART module (ETA a).
<i>t_max_value</i>	The parameter limiting the considered time frame.

5.1.2.2 [LibTopoART.Episodic_TopoART.Episodic_TopoART \(string path \)](#)

This constructor loads a saved Episodic [TopoART](#) network.

Parameters

<i>path</i>	The path of a binary Episodic TopoART file.
-------------	---

5.1.3 Member Function Documentation

5.1.3.1 [override void LibTopoART.Episodic_TopoART.Learn \(decimal\[\] input \) \[virtual\]](#)

This method performs a single training step.

The spatial weights are adapted as in the original [TopoART](#) network. In contrast, the adaptation of the temporal weight $w_{j,2}^{F2,t}$ occurring only in Episodic [TopoART](#) is slightly different: $w_{j,2}^{F2,t}(t+1) = \text{Beta}_j * \text{Max}(t_2^{F1}(t), w_{j,2}^{F2,t}(t)) + (1 - \text{Beta}_j) * w_{j,2}^{F2,t}(t)$ for $j = \text{bm}$ or $j = \text{sbm}$. (Note: $w_{j,1}^{F2,t}$ remains constant over the life time of a node.)

Parameters

<i>input</i>	The input vector to be learnt.
--------------	--------------------------------

Implements [LibTopoART.Fast_TopoART_Base](#).

5.1.4 Member Data Documentation

5.1.4.1 [new static readonly decimal LibTopoART.Episodic_TopoART.file_format_version =0.01m \[static\]](#)

Instance variable `file_format_version` represents the version of the file format used by class [Episodic_TopoART](#).

5.2 LibTopoART_samples.Episodic_TopoART_sample1 Class Reference

Sample using artificial two-dimensional data.

5.2.1 Detailed Description

Sample using artificial two-dimensional data.

Like in "Marko Tscherepanow, Sina Kühnel, and Sören Riechers, 'Episodic Clustering of Data Streams Using a Topology-Learning Neural Network', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 24-29, 2012." an Episodic TopoART network is trained with the well-known Two Spirals dataset. Due to the incorporation of temporal information during learning, Episodic TopoART is capable of creating two clusters each representing one spiral in an unsupervised way. These clusters are formed by the nodes of module b (ETA b).

The resulting network can be visualised using the R script `ShowEpisodicTopoARTResults.R` provided in the subfolder R.

5.3 LibTopoART.F2_output Class Reference

Class `F2_output` provides the output of a single `TopoART` module. It is a compressed version of the output vectors y and c.

Public Member Functions

- `F2_output()`

This constructor sets all instance variables of class `F2_output` to "undefined".

Public Attributes

- decimal `bm_node_activation`

Instance variable `bm_node_activation` represents the activation of the best-matching node.

- long `bm_node_ID`

Instance variable `bm_node_ID` represents the ID of the best-matching node.

- long `bm_cluster_ID`

Instance variable `bm_cluster_ID` represents the cluster ID of the best-matching node.

- decimal `bm_permanent_node_activation`

Instance variable `bm_permanent_node_activation` represents the activation of the best-matching permanent node.

- long `bm_permanent_node_ID`

Instance variable `bm_permanent_node_ID` represents the ID of the best-matching permanent node.

- long `bm_permanent_cluster_ID`

Instance variable `bm_permanent_cluster_ID` represents the cluster ID of the best-matching permanent node.

5.3.1 Detailed Description

Class `F2_output` provides the output of a single `TopoART` module. It is a compressed version of the output vectors y and c.

5.3.2 Constructor & Destructor Documentation

5.3.2.1 `LibTopoART.F2_output.F2_output()`

This constructor sets all instance variables of class `F2_output` to "undefined".

5.3.3 Member Data Documentation

5.3.3.1 `long LibTopoART.F2_output.bm_cluster_ID`

Instance variable `bm_cluster_ID` represents the cluster ID of the best-matching node.

5.3.3.2 `decimal LibTopoART.F2_output.bm_node_activation`

Instance variable `bm_node_activation` represents the activation of the best-matching node.

5.3.3.3 `long LibTopoART.F2_output.bm_node_ID`

Instance variable `bm_node_ID` represents the ID of the best-matching node.

5.3.3.4 `long LibTopoART.F2_output.bm_permanent_cluster_ID`

Instance variable `bm_permanent_cluster_ID` represents the cluster ID of the best-matching permanent node.

5.3.3.5 `decimal LibTopoART.F2_output.bm_permanent_node_activation`

Instance variable `bm_permanent_node_activation` represents the activation of the best-matching permanent node.


5.3.3.6 `long LibTopoART.F2_output.bm_permanent_node_ID`

Instance variable `bm_permanent_node_ID` represents the ID of the best-matching permanent node.

5.4 LibTopoART.Fast_TopoART Class Reference

Class `Fast_TopoART` provides an implementation of the `TopoART` neural network as proposed in "Tscherepanow, Marko (2010). `TopoART`: A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

Inheritance diagram for `LibTopoART.Fast_TopoART`:



Public Member Functions

- [Fast_TopoART](#) (long input_dimension, long module_number, decimal rho_a_value)

This constructor initialises a [TopoART](#) network.
- [Fast_TopoART](#) (string path)

This constructor loads a saved [TopoART](#) network.
- override void [Learn](#) (decimal[] input)

This method performs a single training step.

Additional Inherited Members

5.4.1 Detailed Description

Class [Fast_TopoART](#) provides an implementation of the [TopoART](#) neural network as proposed in "Tscherepanow, Marko (2010). [TopoART](#): A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

Internally, real-valued data are mapped to `long` variables. Therefore, computations are accelerated but less accurate. As a consequence, the results may differ slightly from class [TopoART](#).

Class [Fast_TopoART](#) requires all input to lie in the interval [0,1].

5.4.2 Constructor & Destructor Documentation

5.4.2.1 LibTopoART.Fast_TopoART.Fast_TopoART (long *input_dimension*, long *module_number*, decimal *rho_a_value*)

This constructor initialises a [TopoART](#) network.

Parameters

<i>input_dimension</i>	The dimension of input vectors to be learnt.
<i>module_number</i>	The number of TopoART modules.
<i>rho_a_value</i>	The vigilance parameter of the first TopoART module (TA a).

5.4.2.2 LibTopoART.Fast_TopoART.Fast_TopoART (string *path*)

This constructor loads a saved [TopoART](#) network.

Parameters

<i>path</i>	The path of a binary TopoART file.
-------------	--

5.4.3 Member Function Documentation

5.4.3.1 override void LibTopoART.Fast_TopoART.Learn (decimal[] *input*) [virtual]

This method performs a single training step.

Parameters


<i>input</i>	The input vector to be learnt.
--------------	--------------------------------

Implements [LibTopoART.Fast_TopoART_Base](#).

5.5 LibTopoART.Fast_TopoART_Base Class Reference

Base class providing functionality common to several [TopoART](#) networks.

Inheritance diagram for LibTopoART.Fast_TopoART_Base:



Public Member Functions

- abstract void [Learn](#) (decimal[] input)
This method performs a single training step.
- void [ComputeClusterIDs](#) ()
This method computes the cluster IDs for all neurons.
- [F2_output\[\] GetBMOOutput](#) (decimal[] input)
This method finds the closest category for a given test input.
- void [SaveText](#) (string path)
This method saves the entire network as a text file.
- void [Save](#) (string path)
This method saves the entire network as a binary file.

Static Public Attributes

- static readonly decimal [file_format_version](#) =0.09m
Instance variable `file_format_version` represents the version of the file format used by class [Fast_TopoART](#).
- static readonly string [integer_base_type](#) ="long"
Instance variable `integer_base_type` provides a string containing the data type used for representing integer variables (IDs, parameters, counters, etc.) internally.
- static readonly string [float_base_type](#) ="long"
Instance variable `float_base_type` provides a string containing the data type used for representing floating point variables (input, weights, etc.) internally.

Properties

- long [ModuleNum](#) [get]
Property `ModuleNum` represents the number of [TopoART](#) modules used. (The original [TopoART](#) uses two modules.)
- long [LearningSteps](#) [get]
Property `LearningSteps` represents the total number of performed learning steps.
- decimal [Rho_a](#) [get]
Property `Rho_a` represents the vigilance parameter of the first [TopoART](#) module (TA a).
- decimal [Beta_sbm](#) [get, set]
Property `Beta_sbm` represents the learning rate of the second best-matching nodes.
- long [Tau](#) [get, set]
Property `Tau` represents the parameter tau required for the removal of nodes and edges.

- long `Phi` [get, set]

Property Phi represents the parameter phi required for the removal of nodes and edges as well as for the propagation of input to subsequent TopoART modules.
- decimal `Alpha` [get, set]

Property Alpha represents the choice parameter alpha.
- long[] `NodeNum` [get]

Property NodeNum represents the number of TopoART nodes used by each module.
- long[] `ClusterNum` [get]

Property ClusterNum represents the number of TopoART clusters found by each module.

5.5.1 Detailed Description

Base class providing functionality common to several TopoART networks.

5.5.2 Member Function Documentation

5.5.2.1 void LibTopoART.Fast_TopoART_Base.ComputeClusterIDs()

This method computes the cluster IDs for all neurons.

Implements [LibTopoART.ITopoART](#).

5.5.2.2 F2_output [] LibTopoART.Fast_TopoART_Base.GetBMOOutput(decimal[] input)

This method finds the closest category for a given test input.

Parameters

<code>input</code>	The input vector.
--------------------	-------------------

Returns

An array of type [F2_output](#). Each entry contains the ID of the best-matching node and the corresponding cluster ID for one TopoART module.

Implements [LibTopoART.ITopoART](#).

5.5.2.3 abstract void LibTopoART.Fast_TopoART_Base.Learn(decimal[] input) [pure virtual]

This method performs a single training step.

Parameters

<code>input</code>	The input vector to be learnt.
--------------------	--------------------------------

Implements [LibTopoART.ITopoART](#).

Implemented in [LibTopoART.Episodic_TopoART](#), and [LibTopoART.Fast_TopoART](#).

5.5.2.4 void LibTopoART.Fast_TopoART_Base.Save(string path)

This method saves the entire network as a binary file.

Parameters

<i>path</i>	A string representing the save file.
-------------	--------------------------------------

Implements [LibTopoART.ITopoART](#).

5.5.2.5 void LibTopoART.Fast_TopoART_Base.SaveText (string path)

This method saves the entire network as a text file.

Parameters

<i>path</i>	A string representing the save file.
-------------	--------------------------------------

Implements [LibTopoART.ITopoART](#).

5.5.3 Member Data Documentation**5.5.3.1 readonly decimal LibTopoART.Fast_TopoART_Base.file_format_version =0.09m [static]**

Instance variable `file_format_version` represents the version of the file format used by class [Fast_TopoART](#).

5.5.3.2 readonly string LibTopoART.Fast_TopoART_Base.float_base_type ="long" [static]

Instance variable `float_base_type` provides a string containing the data type used for representing floating point variables (input, weights, etc.) internally.


5.5.3.3 readonly string LibTopoART.Fast_TopoART_Base.integer_base_type ="long" [static]

Instance variable `integer_base_type` provides a string containing the data type used for representing integer variables (IDs, parameters, counters, etc.) internally.

5.6 LibTopoART.ITopoART Interface Reference

Interface summarising the basic [TopoART](#) functionality.

Inheritance diagram for LibTopoART.ITopoART:

**Public Member Functions**

- void [ComputeClusterIDs \(\)](#)
This method computes the cluster IDs for all neurons.
- [F2_output\[\] GetBMOOutput \(decimal\[\] input\)](#)
This method finds the closest category for a given test input.
- void [Learn \(decimal\[\] input\)](#)

- This method performs a single training step.
- void [SaveText](#) (string path)
 - This method saves the entire network as a text file.
- void [Save](#) (string path)
 - This method saves the entire network as a binary file.

Properties

- long[] [NodeNum](#) [get]
 - Property `NodeNum` represents the number of `TopoART` nodes used by each module.
- long[] [ClusterNum](#) [get]
 - Property `ClusterNum` represents the number of `TopoART` clusters found by each module.
- long [ModuleNum](#) [get]
 - Property `ModuleNum` represents the number of `TopoART` modules used. (The original `TopoART` uses two modules.)
- long [LearningSteps](#) [get]
 - Property `LearningSteps` represents the total number of performed learning steps.
- decimal [Beta_sbm](#) [get, set]
 - Property `Beta_sbm` represents the learning rate of the second best-matching nodes.
- decimal [Rho_a](#) [get]
 - Property `Rho_a` represents the vigilance parameter of the first `TopoART` module (TA a).
- long [Tau](#) [get, set]
 - Property `Tau` represents the parameter tau required for the removal of nodes and edges.
- long [Phi](#) [get, set]
 - Property `Phi` represents the parameter phi required for the removal of nodes and edges as well as for the propagation of input to subsequent `TopoART` modules.
- decimal [Alpha](#) [get, set]
 - Property `Alpha` represents the choice parameter alpha.

5.6.1 Detailed Description

Interface summarising the basic `TopoART` functionality.

5.6.2 Member Function Documentation

5.6.2.1 void LibTopoART.ITopoART.ComputeClusterIDs()

This method computes the cluster IDs for all neurons.

Implemented in `LibTopoART.TopoART`, and `LibTopoART.Fast_TopoART_Base`.

5.6.2.2 F2_output [] LibTopoART.ITopoART.GetBMOOutput(decimal[] input)

This method finds the closest category for a given test input.

Parameters

<code>input</code>	The input vector.
--------------------	-------------------

Returns

An array of type `F2_output`. Each entry contains the ID of the best-matching node and the corresponding cluster ID for one `TopoART` module.

Implemented in `LibTopoART.TopoART`, and `LibTopoART.Fast_TopoART_Base`.

5.6.2.3 void LibTopoART.ITopoART.Learn (decimal[] *input*)

This method performs a single training step.

Parameters

<i>input</i>	The input vector to be learnt.
--------------	--------------------------------

Implemented in [LibTopoART.TopoART](#), [LibTopoART.Episodic_TopoART](#), [LibTopoART.Fast_TopoART](#), and [LibTopoART.Fast_TopoART_Base](#).

5.6.2.4 void LibTopoART.ITopoART.Save(string path)

This method saves the entire network as a binary file.

Parameters

<i>path</i>	A string representing the save file.
-------------	--------------------------------------

Implemented in [LibTopoART.TopoART](#), and [LibTopoART.Fast_TopoART_Base](#).

5.6.2.5 void LibTopoART.ITopoART.SaveText(string path)

This method saves the entire network as a text file.

Parameters


<i>path</i>	A string representing the save file.
-------------	--------------------------------------

Implemented in [LibTopoART.TopoART](#), and [LibTopoART.Fast_TopoART_Base](#).

5.7 LibTopoART.ITopoART_R Interface Reference

Interface summarising the basic TopoART-R functionality.

Inheritance diagram for LibTopoART.ITopoART_R:



Public Member Functions

- void [Learn](#) (decimal[] i_vec, decimal[] d_vec)

This method performs a single training step.
- [TopoART_R_Prediction Predict](#) (decimal[] i_vec, bool[] m_i_vec)

This method predicts the dependent variables for a given set of independent variables. Unknown values of independent variables can be signified by setting the corresponding value of m_i_vec to true.

5.7.1 Detailed Description

Interface summarising the basic TopoART-R functionality.

5.7.2 Member Function Documentation

5.7.2.1 void LibTopoART.ITopoART_R.Learn (decimal[] *i_vec*, decimal[] *d_vec*)

This method performs a single training step.

Parameters

<i>i_vec</i>	The input vector (independent variables) to be learnt.
<i>d_vec</i>	The output vector (dependent variables) corresponding to <i>i_vec</i> .

Implemented in [LibTopoART.TopoART_R](#).

5.7.2.2 TopoART_R_Prediction LibTopoART.ITopoART_R.Predict (decimal[] *i_vec*, bool[] *m_i_vec*)

This method predicts the dependent variables for a given set of independent variables. Unknown values of independent variables can be signified by setting the corresponding value of *m_i_vec* to true.

Parameters

<i>i_vec</i>	The input vector (independent variables).
<i>m_i_vec</i>	The mask vector corresponding to <i>i_vec</i> .

Returns

An object of type [TopoART_R_Prediction](#) containing the predicted values for the unknown independent variables and all dependent variables.

Implemented in [LibTopoART.TopoART_R](#).

5.8 LibTopoART.LibTopoART_info Struct Reference

Struct [LibTopoART_info](#) provides some metainformation regarding the respective implementation of [LibTopoART](#).

Static Public Attributes

- static readonly decimal **version** =0.50m

Instance variable version represents the version of LibTopoART.

- static readonly string[] **networks**

Instance variable networks provides a string array containing the networks implemented in the current version of LibTopoART and the corresponding class names.

5.8.1 Detailed Description

Struct [LibTopoART_info](#) provides some metainformation regarding the respective implementation of [LibTopoART](#).

5.8.2 Member Data Documentation

5.8.2.1 readonly string [] LibTopoART.LibTopoART_info.networks [static]**Initial value:**

```
= {
    "Episodic TopoART (class Episodic_TopoART)",
    "TopoART (class TopoART, class Fast_TopoART)",
    "TopoART-R (class TopoART_R)"}
```

Instance variable networks provides a string array containing the networks implemented in the current version of LibTopoART and the corresponding class names.


5.8.2.2 readonly decimal LibTopoART.LibTopoART_info.version =0.50m [static]

Instance variable `version` represents the version of [LibTopoART](#).

5.9 LibTopoART.TopoART Class Reference

Class [TopoART](#) provides an implementation of the [TopoART](#) neural network as proposed in "Tscherepanow, Marko (2010). [TopoART](#): A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

Inheritance diagram for LibTopoART.TopoART:



Public Member Functions

- [TopoART](#) (long input_dimension, long module_number, decimal rho_a_value)

This constructor initialises a [TopoART](#) network.
- [TopoART](#) (string path)

This constructor loads a saved [TopoART](#) network.
- void [ComputeClusterIDs](#) ()

This method computes the cluster IDs for all neurons.
- F2_output[] [GetBMOOutput](#) (decimal[] input)

This method finds the closest category for a given test input.
- void [Learn](#) (decimal[] input)

This method performs a single training step.
- void [SaveText](#) (string path)

This method saves the entire network as a text file.
- void [Save](#) (string path)

This method saves the entire network as a binary file.

Static Public Attributes

- static readonly decimal [file_format_version](#) =0.09m

Instance variable `file_format_version` represents the version of the file format used by class [TopoART](#).
- static readonly string [integer_base_type](#) ="long"

Instance variable `integer_base_type` provides a string containing the data type used for representing integer variables (IDs, parameters, counters, etc.) internally.
- static readonly string [float_base_type](#) ="decimal"

Instance variable `float_base_type` provides a string containing the data type used for representing floating point variables (input, weights, etc.) internally.

Protected Attributes

- readonly long `x_F0_dim`
Instance variable `x_F0_dim` represents the input dimension.
- readonly decimal[] `x_F0`
Instance variable `x_F0` represents the current input vector.

Properties

- long[] `NodeNum` [get]
Property `NodeNum` represents the number of `TopoART` nodes used by each module.
- long[] `ClusterNum` [get]
Property `ClusterNum` represents the number of `TopoART` clusters found by each module.
- long `ModuleNum` [get]
Property `ModuleNum` represents the number of `TopoART` modules used. (The original `TopoART` uses two modules.)
- long `LearningSteps` [get]
Property `LearningSteps` represents the total number of performed learning steps.
- decimal `Rho_a` [get]
Property `Rho_a` represents the vigilance parameter of the first `TopoART` module (TA a).
- decimal `Beta_sbm` [get, set]
Property `Beta_sbm` represents the learning rate of the second best-matching nodes.
- long `Tau` [get, set]
Property `Tau` represents the parameter tau required for the removal of nodes and edges.
- long `Phi` [get, set]
Property `Phi` represents the parameter phi required for the removal of nodes and edges as well as for the propagation of input to subsequent `TopoART` modules.
- decimal `Alpha` [get, set]
Property `Alpha` represents the choice parameter alpha.

5.9.1 Detailed Description

Class `TopoART` provides an implementation of the `TopoART` neural network as proposed in "Tscherepanow, Marko (2010). `TopoART`: A topology learning hierarchical ART network. In Proceedings of the International Conference on Artificial Neural Networks, LNCS 6354 (pp. 157–167). Berlin, Germany: Springer."

Internally, real-valued data are stored in `decimal` variables. Hence, computations are rather slow but very accurate.

Class `TopoART` requires all input to lie in the interval [0,1].

5.9.2 Constructor & Destructor Documentation

5.9.2.1 LibTopoART.TopoART.TopoART (long `input_dimension`, long `module_number`, decimal `rho_a_value`)

This constructor initialises a `TopoART` network.

Parameters

<code>input_dimension</code>	The dimension of input vectors to be learnt.
<code>module_number</code>	The number of <code>TopoART</code> modules.

<i>rho_a_value</i>	The vigilance parameter of the first TopoART module (TA a).
--------------------	---

5.9.2.2 LibTopoART.TopoART.TopoART (string *path*)

This constructor loads a saved [TopoART](#) network.

Parameters

<i>path</i>	The path of a binary TopoART file.
-------------	--

5.9.3 Member Function Documentation

5.9.3.1 void LibTopoART.TopoART.ComputeClusterIDs ()

This method computes the cluster IDs for all neurons.

Implements [LibTopoART.ITopoART](#).

5.9.3.2 F2_output [] LibTopoART.TopoART.GetBMOOutput (decimal[] *input*)

This method finds the closest category for a given test input.

Parameters

<i>input</i>	The input vector.
--------------	-------------------

Returns

An array of type [F2_output](#). Each entry contains the ID of the best-matching node and the corresponding cluster ID for one [TopoART](#) module.

Implements [LibTopoART.ITopoART](#).

5.9.3.3 void LibTopoART.TopoART.Learn (decimal[] *input*)

This method performs a single training step.

Parameters

<i>input</i>	The input vector to be learnt.
--------------	--------------------------------

Implements [LibTopoART.ITopoART](#).

5.9.3.4 void LibTopoART.TopoART.Save (string *path*)

This method saves the entire network as a binary file.

Parameters

<i>path</i>	A string representing the save file.
-------------	--------------------------------------

Implements [LibTopoART.ITopoART](#).

5.9.3.5 void LibTopoART.TopoART.SaveText (string *path*)

This method saves the entire network as a text file.

Parameters

<code>path</code>	A string representing the save file.
-------------------	--------------------------------------

Implements [LibTopoART.ITopoART](#).

5.9.4 Member Data Documentation

5.9.4.1 readonly decimal LibTopoART.TopoART.file_format_version =0.09m [static]

Instance variable `file_format_version` represents the version of the file format used by class [TopoART](#).

5.9.4.2 readonly string LibTopoART.TopoART.float_base_type ="decimal" [static]

Instance variable `float_base_type` provides a string containing the data type used for representing floating point variables (input, weights, etc.) internally.

5.9.4.3 readonly string LibTopoART.TopoART.integer_base_type ="long" [static]

Instance variable `integer_base_type` provides a string containing the data type used for representing integer variables (IDs, parameters, counters, etc.) internally.

5.9.4.4 readonly decimal [] LibTopoART.TopoART.x_F0 [protected]

Instance variable `x_F0` represents the current input vector.


5.9.4.5 readonly long LibTopoART.TopoART.x_F0_dim [protected]

Instance variable `x_F0_dim` represents the input dimension.

5.10 LibTopoART.TopoART_R Class Reference

Class [TopoART_R](#) provides an implementation of the TopoART-R neural network as proposed in "Tscherepanow, Marko (2011). An Extended [TopoART](#) Network for the Stable On-Line Learning of Regression Functions. In Proceedings of the International Conference on Neural Information Processing, LNCS 7063 (pp. 562–571). Berlin, Germany: Springer.

Inheritance diagram for LibTopoART.TopoART_R:

**Public Member Functions**

- [TopoART_R](#) (long i_dimension, long d_dimension, long module_number, decimal rho_a_value)
This constructor initialises a TopoART-R network.

- [TopoART_R](#) (string path)
This constructor loads a saved TopoART-R network.
- void [Learn](#) (decimal[] i_vec, decimal[] d_vec)
This method performs a single training step.
- [TopoART_R_Prediction Predict](#) (decimal[] i_vec, bool[] m_i_vec)
This method predicts the dependent variables for a given set of independent variables. Unknown values of independent variables can be signified by setting the corresponding value of m_i_vec to true.

Static Public Attributes

- new static readonly decimal [file_format_version](#) =0.01m

Instance variable file_format_version represents the version of the file format used by class [TopoART_R](#).

Additional Inherited Members

5.10.1 Detailed Description

Class [TopoART_R](#) provides an implementation of the TopoART-R neural network as proposed in "Tscherepanow, Marko (2011). An Extended [TopoART](#) Network for the Stable On-Line Learning of Regression Functions. In Proceedings of the International Conference on Neural Information Processing, LNCS 7063 (pp. 562–571). Berlin, Germany: Springer.

Class [TopoART_R](#) requires all input and output to lie in the interval [0,1].

5.10.2 Constructor & Destructor Documentation

5.10.2.1 LibTopoART.TopoART_R.TopoART_R (long i_dimension, long d_dimension, long module_number, decimal rho_a_value)

This constructor initialises a TopoART-R network.

Parameters

<i>i_dimension</i>	The dimension of the input vector (independent variables) to be learnt.
<i>d_dimension</i>	The dimension of the output vector (dependent variables) to be learnt.
<i>module_number</i>	The number of TopoART-R modules.
<i>rho_a_value</i>	The vigilance parameter of the first TopoART-R module (TopoART-R a).

5.10.2.2 LibTopoART.TopoART_R.TopoART_R (string path)

This constructor loads a saved TopoART-R network.

Parameters

<i>path</i>	The path of a binary TopoART-R file.
-------------	--------------------------------------

5.10.3 Member Function Documentation

5.10.3.1 void LibTopoART.TopoART_R.Learn (decimal[] i_vec, decimal[] d_vec)

This method performs a single training step.

Parameters

<i>i_vec</i>	The input vector (independent variables) to be learnt.
<i>d_vec</i>	The output vector (dependent variables) corresponding to <i>i_vec</i> .

Implements [LibTopoART.ITopoART_R](#).

5.10.3.2 TopoART_R_Prediction LibTopoART.TopoART_R.Predict (decimal[] *i_vec*, bool[] *m_i_vec*)

This method predicts the dependent variables for a given set of independent variables. Unknown values of independent variables can be signified by setting the corresponding value of *m_i_vec* to true.

Parameters

<i>i_vec</i>	The input vector (independent variables).
<i>m_i_vec</i>	The mask vector corresponding to <i>i_vec</i> .

Returns

An object of type [TopoART_R_Prediction](#) containing the predicted values for the unknown independent variables and all dependent variables.

Implements [LibTopoART.ITopoART_R](#).

5.10.4 Member Data Documentation**5.10.4.1 new static readonly decimal LibTopoART.TopoART_R.file_format_version =0.01m [static]**

Instance variable `file_format_version` represents the version of the file format used by class [TopoART_R](#).

5.11 LibTopoART.TopoART_R_Prediction Class Reference

Class [F2_output](#) contains a prediction made by a TopoART-R network.

Public Member Functions

- [TopoART_R_Prediction \(decimal\[\] *i_vec_prediction*, decimal\[\] *d_vec_prediction*\)](#)
*This constructor sets the instance variables *i_vec_prediction* and *d_vec_prediction* of class [TopoART_R_Prediction](#).*
- void [PrintPredictions \(\)](#)
This method prints the predictions on the console.

Public Attributes

- readonly decimal[] [i_vec_prediction](#)
*Instance variable *i_vec_prediction* represents predictions for unknown independent variables.*
- readonly decimal[] [d_vec_prediction](#)
*Instance variable *d_vec_prediction* provides the predictions for the dependent variables.*

Static Public Attributes

- static readonly decimal [NO_PREDICTION](#) =-1.0m
*Instance variable *NO_PREDICTION* provides a default prediction to signify variables that are presented to the network; i.e., these variables are known and no prediction is computed for them.*

5.11.1 Detailed Description

Class `F2_output` contains a prediction made by a TopoART-R network.

5.11.2 Constructor & Destructor Documentation

5.11.2.1 `LibTopoART.TopoART_R_Prediction.TopoART_R_Prediction(decimal[] i_vec_prediction, decimal[] d_vec_prediction)`

This constructor sets the instance variables `i_vec_prediction` and `d_vec_prediction` of class `TopoART_R_Prediction`.

5.11.3 Member Function Documentation

5.11.3.1 `void LibTopoART.TopoART_R_Prediction.PrintPredictions()`

This method prints the predictions on the console.

5.11.4 Member Data Documentation

5.11.4.1 `readonly decimal[] LibTopoART.TopoART_R_Prediction.d_vec_prediction`

Instance variable `d_vec_prediction` provides the predictions for the dependent variables.

5.11.4.2 `readonly decimal[] LibTopoART.TopoART_R_Prediction.i_vec_prediction`

Instance variable `i_vec_prediction` represents predictions for unknown independent variables.

5.11.4.3 `readonly decimal LibTopoART.TopoART_R_Prediction.NO_PREDICTION = -1.0m [static]`

Instance variable `NO_PREDICTION` provides a default prediction to signify variables that are presented to the network; i.e., these variables are known and no prediction is computed for them.

5.12 LibTopoART_samples.TopoART_R_sample1 Class Reference

Function approximation using TopoART-R.

5.12.1 Detailed Description

Function approximation using TopoART-R.

This sample train a TopoART-R network with 100 points sampled from a sine function. Then, sine values are predicted for 25 random values.

5.13 LibTopoART_samples.TopoART_sample1 Class Reference

Simple TopoART sample.

5.13.1 Detailed Description

Simple TopoART sample.

First, a dataset comprised of 10 samples is learned by a TopoART network. Afterwards, the training samples are slightly modified by random values and used for predicting cluster labels.

5.14 LibTopoART_samples.TopoART_sample2 Class Reference

Sample using artificial two-dimensional data.

5.14.1 Detailed Description

Sample using artificial two-dimensional data.

Train TopoART with a two-dimensional dataset similar to the one used in "Marko Tscherepanow and Sören Riechers, 'An Incremental On-line Classifier for Imbalanced, Incomplete, and Noisy Data', European Conference on Artificial Intelligence (ECAI), Workshop on Active and Incremental Learning (AIL), pp. 18-23, 2012." This dataset comprises six clusters (each containing 15,000 samples) as well as 10,000 noise samples. These samples were mixed randomly.

The resulting network can be visualised using the R script `ShowTopoARTResults.R` provided in the subfolder `R`.

Index

bm_cluster_ID
 LibTopoART::F2_output, 10

bm_node_ID
 LibTopoART::F2_output, 10

bm_node_activation
 LibTopoART::F2_output, 10

bm_permanent_cluster_ID
 LibTopoART::F2_output, 10

bm_permanent_node_ID
 LibTopoART::F2_output, 10

bm_permanent_node_activation
 LibTopoART::F2_output, 10

ComputeClusterIDs
 LibTopoART::Fast_TopoART, 12
 LibTopoART::ITopoART, 15
 LibTopoART::TopoART, 18

d_vec_prediction
 LibTopoART::TopoART_R_Prediction, 22

F2_output
 LibTopoART::F2_output, 9

Fast_TopoART
 LibTopoART::Fast_TopoART, 12

file_format_version
 LibTopoART::Fast_TopoART, 13
 LibTopoART::TopoART, 19
 LibTopoART::TopoART_R, 21

float_base_type
 LibTopoART::Fast_TopoART, 13
 LibTopoART::TopoART, 19

GetBMOOutput
 LibTopoART::Fast_TopoART, 12
 LibTopoART::ITopoART, 15
 LibTopoART::TopoART, 18

i_vec_prediction
 LibTopoART::TopoART_R_Prediction, 22

integer_base_type
 LibTopoART::Fast_TopoART, 13
 LibTopoART::TopoART, 19

Learn
 LibTopoART::Fast_TopoART, 12
 LibTopoART::ITopoART, 15
 LibTopoART::TopoART, 18
 LibTopoART::TopoART_R, 21

LibTopoART, 7

LibTopoART.F2_output, 9

LibTopoART.Fast_TopoART, 10

LibTopoART.ITopoART, 13

LibTopoART.LibTopoART_info, 15

LibTopoART.TopoART, 16

LibTopoART.TopoART_R, 19

LibTopoART.TopoART_R_Prediction, 21

LibTopoART::F2_output
 bm_cluster_ID, 10
 bm_node_ID, 10
 bm_node_activation, 10
 bm_permanent_cluster_ID, 10
 bm_permanent_node_ID, 10
 bm_permanent_node_activation, 10
 F2_output, 9

LibTopoART::Fast_TopoART
 ComputeClusterIDs, 12
 Fast_TopoART, 12
 file_format_version, 13
 float_base_type, 13
 GetBMOOutput, 12
 integer_base_type, 13
 Learn, 12
 Save, 13
 SaveText, 13
 x_F0, 13
 x_F0_dim, 13

LibTopoART::ITopoART
 ComputeClusterIDs, 15
 GetBMOOutput, 15
 Learn, 15
 Save, 15
 SaveText, 15

LibTopoART::LibTopoART_info
 networks, 16
 version, 16

LibTopoART::TopoART
 ComputeClusterIDs, 18
 file_format_version, 19
 float_base_type, 19
 GetBMOOutput, 18
 integer_base_type, 19
 Learn, 18
 Save, 19
 SaveText, 19
 TopoART, 18
 x_F0, 19
 x_F0_dim, 19

LibTopoART::TopoART_R
 file_format_version, 21

Learn, 21
Predict, 21
TopoART_R, 20, 21
LibTopoART::TopoART_R_Prediction
 d_vec_prediction, 22
 i_vec_prediction, 22
 PrintPredictions, 22
LibTopoART_samples, 7
LibTopoART_samples.TopoART_R_sample1, 23
LibTopoART_samples.TopoART_sample1, 23
LibTopoART_samples.TopoART_sample2, 23

NO_PREDICTION
 LibTopoART::TopoART_R_Prediction, 22
networks
 LibTopoART::LibTopoART_info, 16

Predict
 LibTopoART::TopoART_R, 21
PrintPredictions
 LibTopoART::TopoART_R_Prediction, 22

Save
 LibTopoART::Fast_TopoART, 13
 LibTopoART::ITopoART, 15
 LibTopoART::TopoART, 19
SaveText
 LibTopoART::Fast_TopoART, 13
 LibTopoART::ITopoART, 15
 LibTopoART::TopoART, 19

TopoART
 LibTopoART::TopoART, 18
TopoART_R
 LibTopoART::TopoART_R, 20, 21
TopoART_R_Prediction
 LibTopoART::TopoART_R_Prediction, 22

version
 LibTopoART::LibTopoART_info, 16

x_F0
 LibTopoART::Fast_TopoART, 13
 LibTopoART::TopoART, 19
x_F0_dim
 LibTopoART::Fast_TopoART, 13
 LibTopoART::TopoART, 19